How to prepare Pocket PC PDAs





for Brother MPrint

Version 2.0 24 March 2004

Install Brother Mobile Printing Software

1. "Microsoft ActiveSync" software has to have been set up in the PC which will be used to install Brother Mobile Printing Software (=BMPS), prior to installation.

Soft reset the Pocket PC PDA by pushing the reset button to stop all running programs to free storage memory for the installation. Connect the cradle or sync cable to the PC, and place the Pocket PC PDA in the cradle or attach the sync cable.

- 2. Set "MPrint Brother Mobile Printing Software" CD-ROM into CD-ROM drive. "Setup" wizard will run automatically.
- 3. Click the "OK" button in the "Brother Select Language" window.



4. Click the "Pocket PC" icon in the "Brother Mobile Printing Software" window.



5. Click the "Pocket PC PDA" icon in the "Brother mobile printing software" section in the "PocketPC Setup" window.

PocketPC Setup		×
brother	Select the components that you want to install Brother mobile printing software The Brother mobile printing software for Pocket PC will be installed Bonus software PrintPocketCE, the bonus software for	
	Pocket PC, will be installed.	Cancel

6. Select the appropriate version of the Pocket PC OS,

in this example, click the "Pocket PC 2003 PDA" icon in the "Pocket PC 2003" section in the next "PocketPC Setup" window.

PocketPC Setup		×
brother	Select the components that you want to install. Pocket PC 2003 The Brother mobile printing software for Pocket PC 2003 will be installed.	
	Pocket PC 2002 The Brother mobile printing software for Pocket PC 2002 will be installed.	
	Pocket PC The Brother mobile printing software for Pocket PC will be installed.	
	Back Cancel	1

To check the version of the Pocket PC PDA:

On the PDA screen,

- A. Tap "Start".
- B. Tap "Settings".
- C. Tap the "System" tab.
- D. Tap the "About" icon and tap the "Version" tab.
- E. When the name of OS is "Windows® CE" and the version is "3.00.xxxx"
 - it is Pocket PC.

When the name of OS is "Pocket PC" and the version is "3.00.xxxxx"

it is Pocket PC 2002. (TOSHIBA e740)

When the name of OS is "Pocket PC" and the version is "4.20.xxxx"

it is **Pocket PC 2003**. (hp iPAQ h2210, O2 Xda II)

Or check the "Microsoft certification" sticker on the back of the PDA, the version of Pocket PC may be printed there as "Pocket PC 2003" etc.



7. Click the "Next" button in the "InstallShield Wizard" window.



8. Click the "Yes" button in the "License Agreement" window if you agree with the agreement.



9. Check the Setup Type, in this example, click the "Typical" radio button in "Setup Type" window.

Then click the "Next" button.

Then the installation will start.

InstallShield Wizar	rd	X
Setup Type Select the S	Setup Type to install.	No.
CLUB II II A	vpe of Setup you prefer, then click Next.	
• [ypical]	P beram will be installed with the most common optic b commended for most users.	ons.
C Compact	Program will be installed with minimum required opt	ions.
C Cystom	You may choose the options you want to install. Rec for advanced users.	ommended
InstallShield ———	< Back Next >	Cancel

10. Click the "Yes" button to be sure to install Brother Mobile Printing Software into the built-in main memory.

Brother Mobile Printing Software has to be installed into built-in main memory, not into memory cards.

Installing Applications	×		
Install "Brother Task Print" and other and ing installations using the default application install directory?			
1 1 1 1 1 1 1 1 1 1 1 1 1 1 1 1 1 1 1 1	()()え(N) キャンカル		
	119 67		

11. Click the "OK" button in the "Application Downloading Complete" window.



12. Click the "Finish" button to finish the installation in the "InstallShield Wizard" window.



Install PrintPocketCE for Brother software

1. - 4.

STEP1 to STEP4 are the same as the STEPs for Brother Mobile Printing Software.

5. Click the "Printer" icon in the "Bonus software" section in the "PocketPC Setup" window.

PocketPC Setup		×
brother,	Select the components that you want to install. Brother mobile printing software The Brother mobile printing software for Pocket PC will be installed. Brotus software PrintPocketOE, the bonus software for Pocket PC, will be installed.	
	Back	Sancel

6. Select the appropriate version of the Pocket PC OS,

in this example, click the "Pocket PC 2003 PDA" icon in the "PrintPocketCE for Pocket PC 2003" section in the "Bonus Soft Setup" window.

Bonus Soft Setup	<u>×</u>
brother,	Select the components that you want to install. - PrintPocketCE for Pocket PC 2003 - PrintPocketCE for Pocket PC 2003 will be installed.
	PrintPocketCE for Pocket PC 2002 PrintPocketCE for Pocket PC 2002 will be installed.
	PrintPocketCE for Pocket PC PrintPocketCE for Pocket PC will be installed.
	Back Cancel

7. Click the "Yes" button in the "License Agreement" window if you agree with the agreement.



8. Click the "Yes" button to be sure to install PrintPocketCE into the built-in main memory. PrintPocketCE has to be installed into the built-in main memory, not into memory cards.

Installing Applications
Install "FieldSoftware untPocked E for Brother" using the default application install directory?
(1) (1) (1) (1) (1) (1) (1) (1) (1) (1)
Latity Concer Aroon

9. Click the "Finish" button to finish the installation in the "InstallShield Wizard" window.

Application Downloading Complete	×
Please check your mobile device screen to see a addition	is steps are necessary to complete this installation.
<u> </u>	

Delete Brother Mobile Printing Software

- 1. Connect a cradle or a sync cable to the PC, and place the Pocket PC PDA in the cradle or attach the sync cable.
- Select the "Add/Remove Programs..." command from the "Tools" menu in Microsoft ActiveSync.



for Pocket PC and Pocket PC 2002

3. Select the program to be deleted, in this example, click "Brother Clipboard Print" in the "Add/Remove Programs" window.

Then click the "Remove..." button.



4. Click the "OK" button in the "Remove Application" window.



5. Click the "Yes" button in the "Confirm deleting of files" window.

This step is only for the first time of deleting one of Brother Mobile Printing Software.



6. Click the "Finish" button in the "InstallShield Wizard" window.

This step is only for the first time of deleting one of Brother Mobile Printing Software.



for Pocket PC 2003

 Select the program to be deleted, in this example, click "Brother Mobile Printing Software" or "FieldSoftware PrintPocketCE for Brot..." in the "Add/Remove Programs" window. Then click the "Remove..." button.



4. Click the "OK" button in the "Remove Application" window.



Establishing a Bluetooth Connection and Serial Connection – hp iPAQ h2210



1.Tap the "Bluetooth" icon in the bottom right and corner of the iPAQ screen, then select the "Turn Bluetooth ON" command from the menu

 Start
 **
 4 E 10:17

 Image: Start day, February 28, 2004

 Image: Tap here to set owner information

 Image: No upcoming appointments

 Image: No unread messages

 Image: No tasks



The "Bluetooth" icon will turn blue to indicate it is enabled.

Ensure the MW-140BT is switched on and is set into the Bluetooth mode, too.

2.Tap the "Bluetooth" icon and select "Bluetooth Manager" from the menu.

	uetooth Manage 💭 📢 10:19 🛛 🛞
	Bluetooth My Shortcuts
	Ny Shortcuts
	Tap New > Connect!
to	access other devices via Bluetooth
Conn	nect! Ictive Connections
New It	Juis view o 🖸 🔛 🖻
🥂 Co	nnection Wizarc 💭 📢 10:19
	Photootti
	Connection Wizard
<i>)</i> 🖉	Discover the services another device
o s	hortcuts for them.
1	Connect to the Internet
<u> </u>	access point, a cell phone or another
As J	loin a personal network
8-8-8	Connect two or more Bluetooth devices to share files, collaborate or
d P	olay multiplayer games.
E F	stablish a partnership with a cell
🕄 Ca	ncel Next 🌩
_	₩
	Bluetooth Connection Wizard
Devic	e:
	Tap here to choose a device
	to use this screep
To sele	ect a device, tap inside the device
choose	on box above. Arter the list appears, e a device.
Tap 'N	ext' to continue or 'Back' to return to
the pre	evious screen. To exit without sting the connection, tap 'Capertine
Lomple	ncel 👍 Back Nevt 🖒
Comple	
Comple	
Comple Ca	
Comple	
Comple	nnection Wizarc 🗱 📢 10:21 🚯
Comple	nnection Wizarc 🖑 🍕 10:21 🚳 ooth Browser
Complete Com	nnection Wizarc 🗱 🍕 10:21 🚳 ooth Browser e select a device:
Completion Completico Completico Completico Completico Completico Completico	nnection Wizarc 🗯 📢 10:21 🕼 ooth Browser e select a device:
Complete Call Co Bluet Please	nnection Wizarc ## ◀€ 10:21 ⓓ ooth Browser e select a device:
Comple	nnection Wizarc 🗰 📢 10:21 🐽
Comple	nnection Wizarc 🗱 📢 10:21 🐽 ooth Browser e select a device:
Comple	nnection Wizarc 👫 📢 10:21 🐽
Comple Car Bluet Please	nnection Wizarc 👫 📢 10:21 🕼 ooth Browser e select a device:
Comple Ca Ca Bluet Please	nnection Wizarc 👫 📢 10:21 🕼 ooth Browser e select a device:
© Ca	nnection Wizarc 🗰 📢 10:21 🕼 ooth Browser e select a device:
© Ca	nnection Wizarc # ◀ € 10:21 ooth Browser e select a device:

1

3.Tap "New" and select "Connect!" from the menu.

4.Tap "Explore a Bluetooth device" then tap "Next".

5.Tap "Next".

Search for Bluetooth devices will start.

Bluetooth Browser Pleaseselect a device:
MW-
1408180
-
Cancel
View ③
<u>.</u>
🎢 Connection Wizarc 📰 📢 10:22
Bluetooth Connection Wizard
Explore a Bluetooth device
MW-140BT8029
Retrieving services - please wait
\bigcirc
Please select the service(s) offered by this device you would like to create connection
shortcuts for. — <mark>Security</mark> ————————————————————————————————————
Use a secure, encrypted connection
© Cancel ♀ Back Next \$
™
Bluetooth Passkey 📰 📢 10:13 😡
Authentication
Peylog: Mark 4 reactions
Passkey: **** Cancel
Passkey: **** Cancel How to use this screen The Bluetooth paining procedure etablicher a screet what is used in
Passkey: **** Cancel How to use this screen The Bluetooth pairing procedure establishes a secret key that is used in all future connections to authenticate device identity and encrypt data.
Passkey: **** Cancel How to use this screen The Bluetooth pairing procedure establishes a secret key that is used in all future connections to authenticate device identity and encrypt data. Enter your passkey in the field above
Passkey: Passkey: The Bluetooth pairing procedure establishes a secret key that is used in all future connections to authenticate device identity and encrypt data. Enter your passkey in the field above and tap OK to establish a paired relationship with this device.
Paskey: **** Paskey: **** Cancel How to use this screen The Bluetooth pairing procedure establishes a secret key that is used in all future connections to authenticate device identity and encrypt data. Enter your passkey in the field above and tap OK to establish a paired relationship with this device.
Passkey: **** Cancel How to use this screen The Bluetooth pairing procedure establishes a secret key that is used in all future connections to authenticate device identity and encrypt data. Enter your passkey in the field above and tap OK to establish a paired relationship with this device.
Passkey: Passkey: The Bluetooth pairing procedure establishes a secret key that is used in all future connections to authenticate device identity and encrypt data. Enter your passkey in the field above and tap OK to establish a paired relationship with this device. Connection Wizarc ♣ ◄ € 10:24
Paskey: Paskey: Paskey: Lancel How to use this screen The Bluetooth pairing procedure establishes a secret key that is used in all future connections to authenticate device identity and encrypt data. Enter your passkey in the field above and tap OK to establish a paired relationship with this device. Connection Wizarc ↓ 10:24 Bluetooth Connections Wizard Explore a Bluetooth device.
Device: Nut 4 (1957000) Passkey: ***** Cancel How to use this screen The Bluetooth pairing procedure establishes a secret key that is used in all future connections to authenticate device identity and encrypt data. Enter your passkey in the field above and tap OK to establish a paired relationship with this device. Image: Connection Wizarc *** < 10:24
Device: Image: Connection Vizarc Passkey: ***** Connection Vizarc ***** Inture connections to authenticate device identity and encrypt data. Enter your passkey in the field above and tap OK to establish a paired relationship with this device. Image: Connection Wizarc ***** Image: Connection Wizarc ******* Image: Connection Wizarc ****** Image: Connection Wizarc ******* Image: Connection Wizarc ************************************
Device: Image: Connection Vizarce Passkey: ***** Lancel How to use this screen The Bluetooth pairing procedure establishes a secret key that is used in all future connections to authenticate device identity and encrypt data. Enter your passkey in the field above and tap OK to establish a paired relationship with this device. Image: Connection Wizarce: Image: Connection Wizarce:
Device: Image: Automation Passkey: ***** Lancel How to use this screen The Bluetooth pairing procedure establishes a secret key that is used in all future connections to authenticate device identity and encrypt data. Enter your passkey in the field above and tap OK to establish a paired relationship with this device. Image: Connection Wizarce
Device: Image: Connection Vizer Passkey: ***** Lancel How to use this screen The Bluetooth pairing procedure establishes a secret key that is used in all future connections to authenticate device identity and encrypt data. Enter your passkey in the field above and tap OK to establish a paired relationship with this device. Image: Connection Vizer Image
Device: Image: Automation Passkey: ***** Lancel How to use this screen The Bluetooth pairing procedure establishes a secret key that is used in all future connections to authenticate device identity and encrypt data. Enter your passkey in the field above and tap OK to establish a paired relationship with this device. Image: Connection Wizarce **

"MW-140BTxxxx" will be shown in the list.

6.Tap the "MW-140BTxxxx" icon.

and then "Bluetooth Connection Wizard" will run.

7.When asked to enter the Passkey, type in the last four digits of the serial number of the MW-140BT which is on the back of the MW-140BT,

then tap "ok" at the top right of the iPAQ screen.

8.Tap the "Serial Port" icon, then tap "Next".

<i>8</i> 7	Connection Wizarc 📰 🔫	10:25	
*	Bluetooth Connection	Wizard	
	pection shorter they for the set	vice(s) you	
sele	cted were successfully created	l.	
To o Fro	onnect: The Bluetooth Manager "My		
con	nections" screen, double-tap ti nection. Or tap-and-hold the ci . and colort "Connect" from the	onnection	
icon	and select connect from the		
	(Finish 🔗	
		<u> </u>	
Art	Dhatasti Masasa "♥ .4/	10-05	
	Bluetooth Manage 🚛 🤜	10:26	
	y snortcuts		
	۵		
1408	4W- 378029-		
Ser	ial Poi Connect		
	Rename Delete		
	Properties		
My S	hortcuts Active Connections		
New	Tools View 後 匡		
<u>//</u>	Bluetooth Manage 📰 🛋	10:28	
	Bluetooth		
	My Shortcuts		
8			
14	luetooth	×	
24	MW-140BT8029: Serial Por Connecting		
	-		
	Details >>		
L			
My S	hortcuts Active Connections		
New	Tools 🚷 🖭	<u>^</u> ⊠	
<i>1</i>	Bluetooth Manage 岇 📢	10 8 🛞	
8	Bluetooth My Shortcuts	V	
	Nortedd -		
È	•••• 4547-		
140E Seri	BT8029:		
My S	hortcuts Active Connections		
New	Tools Yiew 👸 🔚		

9. When "Shortcut created" is indicated tap "Finish".

10.The "MW-140BTxxxx:Serial Port" icon will appear in the "My Shortcuts" window.

Tap and hold the "MW-140BTxxxx:Serial Port" icon then select "Connect".

Connection will start.

After serial connection is established, the "Serial Port" icon will change from "Service" icon to "Connected" icon

Tap the "Close" button to finish establishing Bluetooth connection and Serial connection.

Set up Brother Mobile Printing Software to print onto MW-140BT via Bluetooth – hp iPAQ h2210



1.Tap "Start",

then select "Programs" from the menu.

- 🚑 🐗 10:30 🛛 🛞 🎊 Programs 1111 6 Brothe MPrint Games alculator ł ٧ Carbon Print Sample cerdisp Diagnostic Toolkit 5 ų Q File Explorer iPAQ Backup iPAQ Image Viewer Č Ŷ ** iTask Microsoft Reader MSN Messenger ₩ -
- 2. Tap "Brother MPrint" in the "Programs" window.



3.Tap and go into the print application software from which you want to print out.In this example, select "Note Print".

🎊 Note Print	<i>#</i> 4 € 10:31 ⊗	
All Folder 🔫		
Name	Date	
Blank Note pwi	Thursday, May O	
Meeting Notes.p	WI Thursday, May U Thursday, May O	
Phone Memo.pw	i Thursday, May O	
To Do.pwi	Thursday, May O	
Printer Graphics Font Print as image		
Printer Seconds		
🎊 Printer setti	ing 🛛 🗱 📢 10:32 🐽	
Printer MW	H1400T	
Port 🖸	48	
Paper size A7	▼	
Printing Orientation	Portrait 🔿 Landscape	
Print mode 🔘	Normal () Global	
Number of copie	es 1 🖨	
	Collate	
	Cancol	
	Cancer	
	<u>^</u> ⊞	

4.Select the "Printer..." command from the "Settings" menu.

5.Select "COM8" as the "Port" for MW-140BT.

The hp iPAQ h2210 is ready for printing onto the MW-140BT via Bluetooth.



The version of Pocket PC on hp iPAQ h2210: Pocket PC 2003

Establishing a Bluetooth Connection and Serial Connection – TOSHIBA e740

<Bluetooth Settings Ver.1.01a>



1.Turn on the Bluetooth Switch which is at the bottom of e740.

When Bluettoth is turned on the "Bluetooth Radio" icon will be indicated.

Ensure the MW-140BT is switched on and is set into the Bluetooth mode, too.



Bluetooth Setting: [®]↑[®] ◀€ 11:13 📀

Con. Dev. Name: Not Connected

Office

Waiting

Version 1.01a Copyright (C) 2001-2002 TOSHIBA Corporation •

Î

Settings Exit

User Mode:

Con. Status:

Remote Device

2.Tap "Start" then select "Programs" from the menu and then tap the "Bluetooth Setup" icon in the "Programs" window.

3.Tap "Remote Device" in the "Bluetooth Settings" window.

🎊 Bluetooth Sett	ings ⁽⁽ †*)	4 € 11:16	8
Remote Devices		•	
Device Name	Sta	atus	
	Page]	
Search options	•		
Delete Ghost De	vice		_
Tools			≝ ^
Bluetooth Sett	ing: ((†))	d ≦ 11•17	
	ing: 1	42 11.17	
		_	
Remote Devices		•	

Now searching for remote devices...

🎊 Bluetooth Setting≤ [©]↑® ◀€ 11:18 🛛 🛞

ी Bluetooth Setting≤ [©]↑³ ◀득 11:26 🛛 😣

•

Status

Refresh

Not Connected

•

Status

Not Connected Not Connected

Not Connected Not Connected Not Connected Not Connected Not Connected

₩ ^

₩ ^

₩.

Tools

Tools

Tools

Remote Devices

Device Name Nokia 6310i Nokia 6310i TUNGSTEN T2 Mike Stokes's C... Nokia 6310i

Remote Devices

MW-140BT8029

ANN CONSTRUCTION ANNO CONSTRUCT ANNO 4.Select the "Device Search" command from the "Tools" menu in the next "Bluetooth Settings" window.

Then Device Search will begin.

Then Bluetooth devices will be listed as the result of Device Search.

5.Tap and hold "MW-140BTxxxx" then select "Refresh".

赶 Bluetooth Setting: ⁽⁽ ¶ ³⁾ ◀< 11:20
Remote Devices 👻
Bovice Name Bluetooth Settings
Now refreshing the
service list
Cancel
Tools
Blockard Security 11 - 5111:20 🚯
_[Bluetooth Passkey (PIN) ———
Use the default PIN when a PIN is not entered.

Requested Bluetooth Jonce
Device Address: 00:02:C7:a0:98:96 Device Name: MW-140BT8029
Tab q w e r t y u i o p []
$\frac{c_{AP} a}{s_{AP}} \frac{s_{AP} a}{s_{AP}} s_$
Tools
🎥 Bluetooth Setting: 🐏 ◄< 11:30 🛛 🗙
Remote Devices 🗸
Device Name Status
MW-140BT802 Service List
A Nokia 6310i
TUNGSTEN T2 Property
MikeD Not Connected
Connected
Tools
Bluetooth Settings *** ◀< 11:33 🕺
MM/-1408T8020

"Refreshina	the	service	list"	will	beain.
rteneorning	uio	001 1100	not	****	bogin.

- 6.When asked to enter the Bluetooth Passkey (PIN), type in the last four digitsof the serial number of the MW-140BTwhich is on the back of the MW-140BT, then tap "OK".
- 7.Tap and hold "MW-140BTxxxx" then select "Service List".

8.Tap and hold "Serial Port" then select "Connect".

Bluetooth	Setting: "T"	4 € 11:33 0 3			
MW-140BT8029					
	_				
Service Nam	Service Name Status Description				
🌋 Serial Port	Not C	Serial Port			
	onnect				
Property					
Defresh					
Refresh					
		I			

🎥 Bluetooth Settings [©] ¶" ◀€ 11:34
MW-140BT8029
Service Name Status Description
Bluetooth Settings
Connecting
\bigcirc
Refresh
Rustasth Esting (*) 41 1124
MW-140870000
MW-1408T0920 Service Name Status Description
MW-140PT0000 Service Name Status Description
MW-140PT0000 Service Name Status Description & Serial Port Conne Serial Port
MW-140PT0000 Service Name Status Description
MW-140PT0000
MW-140PT0000
MW-140PT0009 Service Name Status Description
MW-140PT0000

"Connecting" will begin.

After serial connection has been established, "Serial Port" icon will change from "Service" icon to "Connected" icon, the status indicator for "Serial Port" will change into "Connected" as well.

Now Bluetooth connection and serial port assignment have been established.

<Bluetooth Settings Ver.3.00>

Step1.

Go into "Bluetooth Settings" then "Tools" then "Device Search" then MW-140BT will be searched for and then found.

Step2.

When asked to type in Bluetooth Passkey (PIN), type in the last 4 digits of the serial number of the MW-140BT which is on the back of the MW-140BT, then tap "OK".

Step3.

"Serial Port" will be shown as "Service Name" in the lower part of the window.

Tap and then hold "Serial Port", then select "Connection Registration" After serial connection is established,

"Serial Port" icon will change from "Service" icon to "Registered connection" icon.

Now Bluetooth connection and serial port assignment have been established.

Set up Brother Mobile Printing Software to print onto MW-140BT via Bluetooth – TOSHIBA e740



1.Tap "Start" then select "Programs" from the menu and then tap "Brother MPrint" in the "Programs" window.

Brother MPyint Note Print

🎊 Note	Print	[®] ¶∛ 4 € 2:47 🛛 🛞		
All Folder 🗸				
Name		Date		
Blank Note.pwi Meeting Notes.pwi Memo.pwi Phone Memo.pwi To Do.pwi		Tuesday, January Tuesday, January Tuesday, January Tuesday, January Tuesday, January		
	Printer			
	Graphics			
	Font			
	Print as im	age 🗾 🕨		
Prin er 9	ettings Too	ls 🕅 🗖		

2.Tap and go into the print application software from which you want to print out. In this example, select "Note Print".

3.Select the "Printer..." command from the "Settings" menu.

🎊 Printer s	etting	⁽⁽ † ³⁾ ◀€ 2:48	•
Printer	MW-1408	Г	•
Port			
Paper size	COM4 COM5		7
Printing Orientation	COM7 COM8		=
Print mode	COM9		•
Number of (copies 1	▲ ▼	
		Collate	
	[Cancel	
_			≝ ^

4.Select "COM4" as the "Port" for MW-140BT.

The TOSHIBA e740 is ready for printing onto the MW-140BT via Bluetooth.

The version of Pocket PC on TOSHIBA e740: Pocket PC 2002

🏂 Sel	ttings	° t °	4 € 3:05	•
About				
Microso Version © 1996 All right	ft® Pocket 3.0.11171 6 - 2001 Mic s reserved.	PC (Build 11178) rosoft Corpor	ation.	
This cor U.S. an	nputer prog d internatio	ram is protect nal copyright	ted by laws.	
	Processor:	Intel(R) P× 58.27 MB	(A250	
Exp	ansion slot:	Not in use		
	Owner:			
Version	Device ID	Copyrights		
			B	-

Check and upgrade the ROM on O2 Xda II

To use an Xda II with the MW-140BT the ExtROM version needs to be 1.60.50 or later.



To check the version of ExtROM:



1.Tap "Start",

then select "Settings" from the menu.



2.Tap the "System" tab and tap the "Device Information" icon.

O ₂ Sel	tings:	S.	◀€ 10:07	ⓓ
Device Information				
Item		Des	cription	
ROM N ROM (Radio Protoc	ROM version: ROM date: Radio version: Protocol version:		1.03.00 USA 09/24/03 1.05.12 1337.12	
				_
Version	Hardware	Identity	Call Duration	
			2	<u>–</u>

If there is not "ExtROM" or the version of ExtROM is older than 1.60.50, then you can download "Xda II ROM upgrade" from the O2 web site; http://www.xda-2.co.uk/downloads/xda2-upgrade.html

Establishing a Bluetooth Connection and Serial Connection

– O2 Xda II

Active

0.

Construction of the second sec

О.



👘 📢 11:59 🛞

: 8 Unread

₩ ^

23 March 2004

- 1.Tap the "Bluetooth" icon in the bottom right hand corner of the Xda II screen.
 - Or tap the "O2"icon in the Navigation bar.

Then tap the "Bluetooth" icon in the bottom of the Xda II screen. Or tap the "O2"icon in the Navigation bar.

🎊 Settings	O ₂	👘 📢 12:00 🐽
Bluetooth		
On Bluetooth bonded de	will locati vices.	e and connect to
Off Bluetooth devices an be, our de	will not s id no dev vice.	earch for bonded vice can connect
O Discoverab All devices your devic	ile can find e to crea	and connect to ate a bond.
Mada Davidad	Daviasa	
Mode Bonded	Devices	

1) 🚯

2.Select "ON" or "Discoverable" by clicking the one of the radio buttons.



The "Bluetooth" icon will turn blue to indicate it is enabled.

Ensure the MW-140BT is switched on and is set into the Bluetooth mode, too.

3. Tap the "Bluetooth" icon again then tap "Bonded Device". Then tap"New...".

Search for Bluetooth devices will start.

"MW-140BTxxxx" will be shown in the list.

₩.

发 Settings O2 🖏 ◀€ 12:04
Select a Bluetooth device 🛛 💡
Searching complete.
MW-140BT7886
Settings O2 I < 12:04
Settings O2 Image: Image
$\begin{array}{c} CAP a \le d \ f \ g \ h \ j \ k \ i \ j \ k \ i \ j \ k \ c \ v \ b \ n \ m \ , \ i \ f \ c \ h \ j \ k \ i \ j \ k \ c \ v \ b \ n \ m \ , \ i \ f \ c \ h \ c \ k \ c \ v \ b \ n \ m \ , \ i \ h \ c \ c \ c \ c \ c \ c \ c \ c \ c$
supports Serial Port Profile, would you like to create a Bluetouth Serial Port for it? Yes No 123 1 2 3 4 5 6 7 8 9 0 - = \blacklozenge Tab q w e r t y u i o p [] CAP a s d f g h j k l ; ; Shift z × c v b n m , .] / \leftarrow Ctl áŭ ` \ \downarrow \downarrow \leftarrow

4.Tap "MW-140BTxxxx" and then tap the "Next" button.

5.When asked to enter the Device PIN, type in the last four digits of the serial number of the MW-140BT which is on the back of the MW-140BT, then tap the "Next" button.

6.Tap the "Finish" button.

7.Tap "Yes" to create a Bluetooth Serial Port for the MW-140BT,

and please note the COM5 will be assigned as the Bluetooth Serial Port.

			\frown
🎊 Settings	O ₂	- ∰ - € 12	18 🚯 🚺
Bluetooth			\checkmark
To create a nev an existing bon	v bond, ta d for more	ip New. Tap ar e options.	nd hold
New MW-140BT7	386		
Mode Ronded [
mode bonded t	Jevices		
	_		

8.Tap the "ok" button to finish the establishing Bluetooth connection and Serial connection.

Set up Brother Mobile Printing Software to print onto MW-140BT via Bluetooth – O2 Xda II



1.Tap "Start",

then select "Programs" from the menu.

에 🕂 12:09 🚫 🎊 Programs 🔾 2 6 \Box Games Album Brother MPrint 11 10 Calendar Calculator Camera "A Q cerdisp Clear¥ue PDF Clear¥ue PPT 5 Ŷ 1

MIDlet Manager 2.Tap "Brother MPrint".



File Explorer Microsoft Reader

- 3. Tap and go into the print application software from which you want to print out.
 - In this example, select "Note Print".

🎊 Note Print 🔾 – 🚮 ◀€ 12:10 ጰ	
All Folder 🗸	4.8
Name Date	
Blank Note.pwi 01 September 2 Maating Nates pwi 01 September 2.	
Meeting Notes.pwi 01 September 2 Memo.pwi 01 September 2	
Phone Memo.pwi 01 September 2	
To Do.pwi UI September 2	
Printer	
Graphics	
Print as image	
Printer Settings Tools 🔤 🔺	
🚰 Printer set 🔾 🛛 🖓 📲 12:10 😡	5 9
Printer MW-140BT -	0.0
	2
Port COMP	
Paper size	
Printing COM,	
Orientation COM8	
Print mode Contractor Contractor	
Number of copies	
Collate	
Cancel	
All Folder 🗸	6. I
Name Date	+
Blank Note.pwi 01 September 2	ι
Meeding Swine Conservation States 2	
Phone Memo,pwi 01 September 2	
The sector of september 2	٦
\frown	
Print	
Print Preview	
Print Preview Quit	
Print Preview Quit Printer Settings cools	
Print Preview Quit Printer Settings ools	
Print Preview Quit Printer Settings ools	6 -1
Print Preview Quit Printer Settings ools ▲	B Proces
Print Preview Quit Printer Settings ools Image: Setting state of the set of the se	Proces
Print Preview Quit Printer Settings ools Image: Setting on the set of t	Proces Printing

4.Select the "Printer..." command from the "Settings" menu.

5.Select "MW-140BT" as the "Printer" and select "COM5" as the "Port" for MW-140BT.

6.To ensure the settings sre OK,tap the file name which you want to print out.In this example, select "Phone Memo.pwi".Then select the "Print" command from the "Printer" menu.

Preparing print data. Please wait a moment.	Printing
	100%
Cancel	Cancel

Print procedure will start then the print out will eject from the MW-140BT. Set up PrintPocketCE for Brotehr printing software to print onto MW-140BT via Bluetooth – O2 Xda II



1.Tap "Start",

then select "Programs" from the menu.

👘 📢 12:13 🛞 🎊 Programs 🔾 8 X Ø Photo Contacts Pocket Excel Pictures V W Pocket MSN Pocke Word PrintPocke for Brothe . Terminal Services Client 5IM Manage SIM Tool Kit Wireless Modem xmail from 02 xBackup Ţ

2.Tap "PrintPocke...for Brother".



If "About" screen appears, tap the "OK" button.

DrintPo	ocke ဝ 2	- • ¶ €€	13:04 😣
🖰 All Fold	ers 🗸		Name 👻
Appoint	mentPro	01/09/0)3 Ob
Connect	ionProte	01/09/0)3 Ob
Dilater I	sprotect	01/09/0	
	.og.cxc	01/09/0	13 IK
Doc Option	s 😰 🕷	\bowtie	
🎊 PrintP	ocke		13:01 🐽
Printe	Brother MW	-140BT	-
Port:	Con		
Color/Mono:	Infrared Network: PC	with share	ed pripter
Paper Size:	Network: IP	Printer	sa princor
- Orientatio	Bluetooth: F Bluetooth: A	IP iPAQ Invcom Prin	t Module
Portra	Bluetooth: 9	ocket CF C	ard
O Lands	Bluetooth: E	elkin	
	COM2:		
Start	ZOM4:		
	COM5: COM6:		
	COMP.		
	COM9:		
	Print to File LPT1:		
Reint D.	ncka 🔿	231-42	13 10 60
			13-10 -019
Printer:	Brother MW	-140BT	
Port:	COM5:		•
Color/Mono:	Monochrom	e (B & W)	•
Paper Size:	Custom		•
_Γ Orientatio	п —— гРа	per Dimens	ions
Portra	it V	Vidth 7.4c	m
Otinds	cape H	eight 10.5	icm
Chart			Canaal
Printing	Mor Settir	e ngs	Printing

- 3.Select the file which you want to print out. I this example, select "RilNty_Log.txt",
 - then tap the "Print Plain Text" button in the next screen.

4.Select "Brother MW-140BT" as "Printer", select "COM5" as "Port".

5.Tap the "ok" button or "Start Printing" then printing will start. If you don't want to print out anything here, tap the "Cancel" button to stop printing.

The O2 Xda II is ready for printing onto the MW-140BT from PrintPocketCE for Brother printing software via Bluetooth.

The version of Pocket PC on O2 Xda II: Pocket PC 2003 Phone Edition



Print with Brother Mobile Printing Software to print onto MW-140BT via Bluetooth

Refer to "Software Guide".

Change the device name and the PIN code of the MW-140BT

Because the default device name of the MW-140BT includes the last four digits of it's serial number and the default PIN code of the MW-140BT is the last four digits of it's serial number itself, so it is possible to ensure the high security by changing both the device name and the PIN code of the MW-140BT.

To change the device name and the PIN code: using the **hp iPAQ h2210** in this exaple



1.Tap "Start" then select "Programs" from the menu.Tap "Brother MPrint" in the "Programs" window.Tap "Mprint Utility".

🎊 MPrint Utility 💦 🗮 📢 10:23 🐽
Printer MW-140BT
General Bluetooth (1)
Bluetooth (2) Reset settings

2.Tap "Bluetooth (2)". Ensure "COM8" is selected as "Port" and the MW-140BT is switched on and is set into the Bluetooth mode, too.

(different devices may require the selection of a different COM port)

<i>ß</i> MPrint Utility 👘 🗱 📢 10:24 🐽
Device name
Specify name (max. 12 digits).
Device name
PIN code (password)
Activate PIN code.
PIN code:
To check, type in the 4-digit number twice.
Connect Cancel
₩

3.Tap "Connect".

Bluetooth Cons Bluetooth Brows	sole #ª ◀€ 10:25 🚳 ser a device
MW- 140BT80	
View 🙆	Cancel
TIEW 🕑	
🔏 Bluetooth Cons	sole # ◀€ 10: 6 🚳
Authenticatio	h n
Device: MW-1	10070000
Passkey: ****	
	cancel
 How to use this set The Bluetooth pa 	irina procedure
establishes a secre	et key that is used in
	6 7 8 9 0 - = 4
	3 h j k l ; '
Shift z x c v Ctl áü ` \	b n m , . / ←
MPrint Utility	
Device name —	
Specify name (m	iax. 12 digits).
Device name M	W-140BT8029
DIN code (need	uord)
Activate PI	N code.
PIN code: **	***
To check, type i number twice.	n the 4-digit
Set	Cancel
0	
MPrint Utility	4 € 10:29 @
Specify name (m	nax. 12 digits).
Device name M	y MW-140BT
PIN code (pass	word)
M Advice F1	N LOGE.
PIN code:	***
number twice.	

Cancel

4.Tap to select the MW-140BT with which you want to connect.

5.When asked to enter the Passkey, type in the last four digits of the serial number of the MW-140BT which is on the back of the MW-140BT,

then tap "ok" at the top right of the iPAQ screen.

6.The current settings of the "Device name" and the "PIN code" will be shown.

7.Change the "Device name" and the "PIN code" as you wish, then tap "Set".



8.Tap the "ok" button.

The settings are specified.

To change the device name and the PIN code: using the **O2 Xda II** in this example



1.Tap "Start" then select "Programs" from the menu.Tap "Brother MPrint" in the "Programs" window.Tap "Mprint Utility".

🎊 MPri	nt Util ဝ ₂	∄∎⊀	11:28	ⅆ
P	rinter MW-14	40BT	•	>
	Genera	al		
(Bluetoot Bluetoot	h (1) h (2)	>	
	Reset set	tings		
			E	ਤ ^

2.Tap "Bluetooth (2)".

Ensure "COM5" is selected as "Port" and the MW-140BT is switched on and is set into the Bluetooth mode, too.

(different devices may require the selection of a different COM port)

🎊 MPrint Util 🔾 🛛 👘 📢 11:29 🐠
Device name
Specify name (max. 12 digits).
Device name
PIN code (password)
✓ Activate PIN code.
PIN code:
To check, type in the 4-digit number twice.
Connect Cancel

Image: State of the state
MW-140BT8029 wants to bond with your device over Bluetooth. Add MW-140BT8029 to your bonded devices lot
PIN code:
Connect Cancel
₩

3.Tap	"Connect".
-------	------------

4. Tap the "OK" button in the "Bluetooth" pop-up menu.

윤 Start 🔾 🦂 👫 4€ 11:30
Enter Device Bluetooth PIN
Enter a Bluetooth PIN of your choice to bond with MW-140BT8029. The same PIN must be entered on both devices.
Please check your device's instruction manual to learn how to answer to PIN requests.
Device PIN: ****
Cancel Back Next
123 1 2 3 4 5 6 7 8 9 0 - = € Tab q w e r t y u i o p [] CAP a s d f g h j k l ; ' Shift z x c v b n m , . / + → Ctláů` \ _ ↓ ↑ € →
🔏 MPrint Util 🔾 🖞 ┥€ 11:32 🚳
Device name
Specify name (max. 12 digits).
Device name MW-140BT8029
Activate PIN code.
PIN code: ****
To check, type in the 4-digit
Set Cancel
Device name Specify name (max. 12 digits). Device name My MW-140BT
PIN code (password)
PIN code: **** ****
To cheeky by a is the statiget number twice.
Set Cancel
🎉 MPrint Util 🔾 🖞 ଐ ଐ€ 11:33
Specify name (max. 12 digits).
MPrint Utility
The settings are specified.
To check, type in the 4-digit number twice.
To check, type in the 4-digit number twice.

5.When asked to enter the Device PIN, type in the last four digits of the serial number of the MW-140BT which is on the back of the MW-140BT, then tap the "Next" button.

6.The current settings of the "Device name" and the "PIN code" will be shown.

7.Change the "Device name" and the "PIN code" as you wish, then tap "Set".

8. Tap the "ok" button.

The settings are specified.